


Scientifica 7 Special Resource Pack Installation Instructions

Contents

Updating a standalone installation of the Scientifica 7 ICT Power Pack	2
Updating a network installation of the Scientifica 7 ICT Power Pack	2
Installing the Special Resource Pack separately on a standalone computer	3
Installing the Special Resource Pack separately on a network	4
Installation Notes and Troubleshooting	5
Launching	5
Uninstallation	5
Technical Support	5

If you already have the Scientifica 7 ICT Power Pack installed on your computer or network, it is possible to update the program with the Special Resource Pack resources by following the instructions on this page.



Updating a standalone installation of the Scientifica 7 ICT Power Pack

- 1 The CD-ROM should auto-run when you insert it in your CD-ROM drive. If your auto-run is disabled, double-click on the 'JC_SetupSelection.exe' file listed in the contents of the CD-ROM.
- 2 The Scientifica 7 ICT Power Pack installation will be detected on your computer, and the Installation Selection window will appear. Click 'Yes, add these resources to the Scientifica 7 ICT Power Pack'.
- 3 The new files and resources will be installed. Do not close any windows or attempt to launch the program until an installation complete message is displayed.
- 4 It is recommended that you restart your machine once the installation is complete.

Updating a network installation of the Scientifica 7 ICT Power Pack

At the server:


- 1 Stop the 'Just Click' **service** that is running.
- 2 The CD-ROM should auto-run when you insert it in your CD-ROM drive. If your auto-run is disabled, double-click on the 'JC_SetupSelection.exe' file listed in the contents of the CD-ROM.
- 3 The Scientifica 7 ICT Power Pack installation will be detected on your server, and the Installation Selection window will appear. Click 'Yes, add these resources to the Scientifica 7 ICT Power Pack'.
- 4 The new files and resources will be installed on the server. Do not close any windows or attempt to launch the program until an installation complete message is displayed.
- 5 Start the 'Just Click' service again.

At each client machine:

N.B.: Once the server update has been carried out, client machines will be unable to access the Scientifica 7 ICT Power Pack until they are also updated.

- 1 The CD-ROM should auto-run when you insert it in your CD-ROM drive. If your auto-run is disabled, double-click on the 'JC_SetupSelection.exe' file listed in the contents of the CD-ROM.
- 2 The Scientifica ICT Power Pack installation will be detected on the client machine, and the Installation Selection window will appear. Click 'Yes, add these resources to the Scientifica 7 ICT Power Pack'.
- 3 Some files will be updated at the client machine. Do not close any windows or attempt to launch the program until an installation complete message is displayed.

If you do not have the Scientifica 7 ICT Power Pack, or do not wish to combine the resources, you may install the Special Resource Pack separately by following the instructions on the next two pages.



Installing the Special Resource Pack separately on a standalone computer

- 1 The CD-ROM should auto-run when you insert it in your CD-ROM drive. If your auto-run is disabled, double-click on the 'JC_SetupSelection.exe' file listed in the contents of the CD-ROM.
- 2 If you are prompted, click 'No, install the Special Resource Pack separately.'
- 3 Before you install the Special Resource Pack, you will need to install each of the required plug-ins that you do not already have. The installation program will check which of the required plug-ins are not installed on your computer and allow you to install the plug-ins by selecting them from the Installation Menu. Click on a plug-in and follow the instructions on screen to install it.
N.B.: You will return to the Installation Menu at the end of each plug-in installation, so that you can perform further installations if necessary. It is recommended that you perform each of the installations in the order listed.
- 4 From the Installation Menu, click '4. Scientifica SRP7' to install the main program.
N.B.: You will not be able to select this option and install the main program until all of the required plug-ins have been installed (see step 3).
- 5 Click 'Next', then click 'Yes' if you accept the terms of the licence agreement.
- 6 Select the 'Standalone' set-up type, then click 'Next'.
- 7 Click 'Browse' if you wish to change the location for the installation. Otherwise, click 'Next' to install to the default location.
- 8 Choose a password that all teachers will use to enter the Special Resource Pack. Remember to keep a note of this password!
- 9 If you are satisfied with the installation information provided in the summary, click 'Next' to begin copying the main program files and all of the resources to the standalone computer.
- 10 Click 'Finish' when the system prompts you, then click 'Close' to close the Installation Menu.

Installing the Special Resource Pack separately on a network

At the server:

- 1 Perform steps 1–5 as for installing the Special Resource Pack separately on a standalone computer (see page 3).
- 2 Select the 'Server' set-up type, then click 'Next'.
- 3 Click 'Browse' if you wish to change the location for the installation. Otherwise, click 'Next' to install to the default location.
- 4 Choose a password that all teachers will use to enter the Special Resource Pack. Remember to keep a note of this password!
- 5 Enter the server's IP address and alter the port number if necessary (see Installation Notes and Troubleshooting on page 5). Then enter the path under which the installation will be made available in the format '`\\<IP ADDRESS>\<SHARE_NAME>`'. Replace IP_ADDRESS with the IP of the server and SHARE_NAME with the name of the shared directory which will be found in the Windows network environment (see step 8) e.g. '`\\10.1.1.32\Scientifica SRP7`'. Please note that in some network environments, it may be necessary to use the server name instead of the IP address (see Installation Notes and Troubleshooting on page 5).
- 6 If you are satisfied with the installation information provided in the summary, click 'Next' to begin installing the main program files and all of the resources to your server.
- 7 Click 'Finish' when the system prompts you, then click 'Close' to close the Installation Menu.
- 8 Locate the 'Scientifica SRP7' folder (default location '`\\Program Files\Nelson Thornes \Just Click\Scientifica SRP7`') that has been installed and share the folder for all users. The share name for this folder must be the name entered as part of the path in step 5.

At each client machine:

- 1 Perform steps 1–5 as for installing the Special Resource Pack separately on a standalone computer (see page 3).
- 2 Select the 'Client' set-up type, then click 'Next'.
- 3 Click 'Browse' if you wish to change the location for the installation. Otherwise, click 'Next' to install to the default location.
- 4 Enter the server's IP address and alter the port number if necessary, then click 'Next'.
- 5 If you are satisfied with the installation information provided in the summary, click 'Next' to begin installing the files that are required by each client machine.
- 6 Click 'Finish' when the system prompts you, then click 'Close' to close the Installation Menu.



Installation Notes and Troubleshooting

Ports

If you are installing the Special Resource Pack separately on a network, and a Just Click service for another Just Click program has previously been installed, you will need to alter the port number displayed during the installation to avoid any conflict between programs.

IP addresses

In some network environments entering the IP address during a network installation may not work. You may encounter problems logging in to the Special Resource Pack or viewing the resources once logged in. Use the server name instead. To replace the IP address with the server name without having to re-install the software:

- 1 Locate the folder 'config' in the 'Scientifica SRP7' folder at the server.
- 2 Open the file 'justclick.properties' using a text editor.
- 3 Replace the IP address with the server name in the 'networkpath' entry e.g. '\\THE_SERVER\Scientifica SRP7'. Reboot the server and test the program.
- 4 If you still encounter problems, repeat the above process, changing the entry for 'serverhost' to the server name, for example 'THE_SERVER'.
- 5 If you still encounter problems, repeat the above process at a client machine, changing the entry for 'serverhost' to the server name, for example 'THE_SERVER'.

Passwords

If you forget the teacher password, or want to change it, follow the instructions given in the 'password_readme' file located in the 'Scientifica' or 'Scientifica SRP7' folder on your server or standalone computer.

Launching

If you have updated your installation of the Scientifica 7 ICT Power Pack, launch Scientifica in the normal way to access the Special Resource Pack resources from the Resource Finder and Book page screens.

If you have installed the Special Resource Pack separately, click 'Start > Programs > Nelson Thornes > Just Click > Scientifica SRP7' or double-click the 'Scientifica SRP7' shortcut on the desktop.

Uninstallation

It is only possible to uninstall the Special Resource Pack if it has been installed separately. Click 'Start > Settings > Control Panel', then 'Add/Remove programs'. Locate 'Just Click – Scientifica Special Resource Pack 7' in the list of currently installed programs and click 'Change/Remove'. Follow the instructions on screen.

Technical Support

For technical support, please visit www.nelsonthornes.com/justclick
e-mail technicalsupport@nelsonthornes.com
or call Nelson Thornes Technical Support line on **+44 (0)1242 267383**.

Scientifica Special Resource Pack 7 contains Macromedia Flash™ Player software by Macromedia, Inc., Copyright © 1995–2000 Macromedia, Inc. All rights reserved. Macromedia and Flash are trademarks of Macromedia, Inc.

